

This document provides additional assistance with wiring your Extron IP Link Pro Control Processor to your device. Different components may require a different wiring scheme than those listed below.

For complete operating instructions, refer to the user's manual for the specific IP Link Pro Control Processor or the documentation supplied by the manufacturer of the controlled device.

For more information on using Global Scriptor Modules, refer to the "[Guide to Using Scriptor Modules](#)" document.

## Device Specifications

Device Type: Camera  
Manufacturer: Vaddio  
Firmware Version: N/A  
Model(s): RoboSHOT 12 HDMI, RoboSHOT 30 HDMI, RoboSHOT 20 UHD, RoboSHOT 40 UHD

## Tested on the Following Software and Firmware Versions

IP Link Pro Control Processor Firmware	Global Scriptor Version
3.16.0000-b013	2.17.0

## Version History

Module Version	Date	Notes
1_1_2_1	12/1/2022	Fixed Device ID parameter for Serial control.
1_1_2_0	3/24/2021	Updates to Ethernet module: <ul style="list-style-type: none"><li>○ Added status to Power</li><li>○ Removed Firmware Status</li><li>○ Fixed authentication</li></ul> Added Auto Focus status.
1_0_5_0	10/7/2019	Added model RoboSHOT 40 UHD.
1_0_4_0	3/6/2019	Added Iris command and Auto Iris status to Ethernet
1_0_2_0	11/16/2017	Initial Version

## Module Notes

- Unidirectional variable must be set to 'True' if status is not required. Default value is 'False'.  
Example: `InterfaceName.Unidirectional = 'True'`
- connectionCounter variable must be set to the number of queries that will be sent to the device before displaying 'Disconnected' if no response is received. Default value is 15.  
Example: `InterfaceName.connectionCounter = 5`
- If login credentials are required, devicePassword and deviceUsername must be set accordingly. devicePassword and deviceUsername default values are password and admin respectively.  
Example: `InterfaceName.devicePassword = 'extron'`
- DeviceID variable must be set accordingly. Default value is '1'. DeviceID ranges from 1 to 7.  
Example: `InterfaceName.DeviceID = '1'`
  - For Serial protocol only, if there is no option to set the camera ID in the camera's settings menu, then according to Vaddio it should be set to 1 within the module

## Supported Classes and Examples

<b>SerialClass</b>
<code>InterfaceName = ModuleName.SerialClass(ProcessorName, 'COM1', Model='RoboSHOT 12 HDMI')</code>
<b>SerialOverEthernetClass</b>
<code>InterfaceName = ModuleName.SerialOverEthernetClass('192.168.254.254', 2001, Model='RoboSHOT 12 HDMI')</code>
<b>EthernetClass</b>
<code>InterfaceName = ModuleName.EthernetClass('192.168.254.254', 23, Model='RoboSHOT 12 HDMI')</code>

## Control Commands (Serial)

Format with Qualifier:

```
InterfaceName.Set(Command, Value, {'Qualifier Key': 'Qualifier Value'})
```

Format without Qualifier:

```
InterfaceName.Set(Command, Value)
```

Command AutoFocus	Value 'On'	Value 'Off'	
# AutoFocus example InterfaceName.Set('AutoFocus', 'On')			
Command Backlight	Value 'On'	Value 'Off'	
# Backlight example InterfaceName.Set('Backlight', 'On')			
Command Focus	Value 'Near'	Value 'Far'	Value 'Stop'
Qualifier Key 'Speed'	Qualifier Value '0' – '7'		
# Focus example InterfaceName.Set('Focus', 'Near', {'Speed': '0'})			
Command Freeze	Value 'On'	Value 'Off'	
# Freeze example InterfaceName.Set('Freeze', 'On')			
Command Iris	Value 'Reset'	Value 'Up'	Value 'Down'
# Iris example InterfaceName.Set('Iris', 'Reset')			
Command Mute	Value 'On'	Value 'Off'	
# Mute example InterfaceName.Set('Mute', 'On')			
Command PanTiltZoom	Value 'Up' 'Right' 'Stop'	Value 'Down' 'In'	Value 'Left' 'Out'
Qualifier Key 'Pan Speed'	Qualifier Value '1' – '24'		
Qualifier Key 'Tilt Speed'	Qualifier Value '1' – '20'		
Qualifier Key 'Zoom Speed'	Qualifier Value '0' – '7'		
# PanTiltZoom example InterfaceName.Set('PanTiltZoom', 'Up', {'Pan Speed': '1', 'Tilt Speed': '1', 'Zoom Speed': '0'})			
Command Power	Value 'On'	Value 'Off'	
# Power example InterfaceName.Set('Power', 'On')			

Command <b>PresetRecall</b>	Value '1' – '16'		
# PresetRecall example InterfaceName.Set('PresetRecall', '1')			
Command <b>PresetSave</b>	Value '1' – '16'		
# PresetSave example InterfaceName.Set('PresetSave', '1')			
Command <b>RecallTriSync</b>	Value '0' – '15'		
# RecallTriSync example InterfaceName.Set('RecallTriSync', '0')			
Command <b>SetTriSync</b>	Value '0' – '15'		
Qualifier Key <b>'Speed'</b>	Qualifier Value 1 to 26 in steps of 1		
# SetTriSync example InterfaceName.Set('SetTriSync', '0', {'Speed': 26})			
Command <b>WhiteBalance</b>	Value 'Auto'	Value 'Indoor'	Value 'Outdoor'
	'One Push White Balance'	'ATW'	'Manual'
	'One Push Trigger'	'Outdoor Auto'	'Sodium Lamp Auto'
	'Sodium Lamp'	'Sodium Lamp Outdoor Auto'	
# WhiteBalance example InterfaceName.Set('WhiteBalance', 'Auto')			

## Status Available (Serial)

For all commands, call Update to receive the latest status. ConnectionStatus does not support the Update function and is triggered by the device providing a successful response to other Update function calls.

Format with Qualifier:

```
InterfaceName.Update(Command, {'Qualifier Key': 'Qualifier Value'})
Value = InterfaceName.ReadStatus(Command, {'Qualifier Key': 'Qualifier Value'})
InterfaceName.SubscribeStatus(Command, {'Qualifier Key': 'Qualifier Value'},
```

FeedbackHandler)

FeedbackHandler will be called only when the specified qualifier gets a new status.

Format without Qualifier:

```
InterfaceName.Update(Command)
Value = InterfaceName.ReadStatus(Command)
InterfaceName.SubscribeStatus(Command, None, FeedbackHandler)
FeedbackHandler will be called when any qualifier gets a new status.
```

Command	Value	Value
<b>AutoFocus</b>	'On'	'Off'
# AutoFocus example InterfaceName.Update('AutoFocus') Value = InterfaceName.ReadStatus('AutoFocus') InterfaceName.SubscribeStatus('AutoFocus', None, FeedbackHandler)		
Command	Value	Value
<b>Backlight</b>	'On'	'Off'
# Backlight example InterfaceName.Update('Backlight') Value = InterfaceName.ReadStatus('Backlight') InterfaceName.SubscribeStatus('Backlight', None, FeedbackHandler)		
Command	Value	Value
<b>ConnectionStatus</b>	'Connected'	'Disconnected'
# ConnectionStatus example Value = InterfaceName.ReadStatus('ConnectionStatus') InterfaceName.SubscribeStatus('ConnectionStatus', None, FeedbackHandler)		
Command	Value	Value
<b>Freeze</b>	'On'	'Off'
# Freeze example InterfaceName.Update('Freeze') Value = InterfaceName.ReadStatus('Freeze') InterfaceName.SubscribeStatus('Freeze', None, FeedbackHandler)		
Command	Value	Value
<b>Mute</b>	'On'	'Off'
# Mute example InterfaceName.Update('Mute') Value = InterfaceName.ReadStatus('Mute') InterfaceName.SubscribeStatus('Mute', None, FeedbackHandler)		
Command	Value	Value
<b>Power</b>	'On'	'Off'
# Power example InterfaceName.Update('Power') Value = InterfaceName.ReadStatus('Power') InterfaceName.SubscribeStatus('Power', None, FeedbackHandler)		

## Global Scripter Module Communication Sheet

Command	Value	Value	Value
<b>WhiteBalance</b>	'Auto'	'Indoor'	'Outdoor'
	'One Push White Balance'	'ATW'	'Manual'
	'One Push Trigger'	'Outdoor Auto'	'Sodium Lamp Auto'
	'Sodium Lamp'	'Sodium Lamp Outdoor Auto'	
<pre># WhiteBalance example InterfaceName.Update('WhiteBalance') Value = InterfaceName.ReadStatus('WhiteBalance') InterfaceName.SubscribeStatus('WhiteBalance', None, FeedbackHandler)</pre>			

## Control Commands (Ethernet)

Format with Qualifier:

InterfaceName.Set(Command, Value, {'Qualifier Key': 'Qualifier Value'})

Format without Qualifier:

InterfaceName.Set(Command, Value)

Command	Value	Value	
AutoFocus	'On'	'Off'	
# AutoFocus example InterfaceName.Set('AutoFocus', 'On')			
Command	Value	Value	
AutoIris	'On'	'Off'	
# AutoIris example InterfaceName.Set('AutoIris', 'On')			
Command	Value	Value	Value
Focus	'Near'	'Far'	'Stop'
Qualifier Key	Qualifier Value		
'Speed'	'0' – '7'		
# Focus example InterfaceName.Set('Focus', 'Near', {'Speed': '0'})			
Command	Value		
Iris	0 to 13 in steps of 1		
# Iris example InterfaceName.Set('Iris', 13)			
Command	Value	Value	Value
Pan	'Left'	'Right'	'Stop'
Qualifier Key	Qualifier Value		Qualifier Value
'Speed'	'1' – '24'		'Default'
# Pan example InterfaceName.Set('Pan', 'Left', {'Speed': '1'})			
Command	Value	Value	
Power	'On'	'Off'	
# Power example InterfaceName.Set('Power', 'On')			
Command	Value		
PresetRecall	'1' – '16'		
# PresetRecall example InterfaceName.Set('PresetRecall', '1')			
Command	Value		
PresetSave	'1' – '16'		
# PresetSave example InterfaceName.Set('PresetSave', '1')			
Command	Value	Value	Value
Tilt	'Up'	'Down'	'Stop'
Qualifier Key	Qualifier Value		Qualifier Value
'Speed'	'1' – '20'		'Default'
# Tilt example InterfaceName.Set('Tilt', 'Up', {'Speed': '1'})			

## Global Scripter Module Communication Sheet

<b>Command</b> <b>Zoom</b>	Value 'In'	Value 'Out'	Value 'Stop'
<b>Qualifier Key</b> <b>'Speed'</b>	Qualifier Value '1' – '7'	Qualifier Value 'Default'	
# Zoom example InterfaceName.Set('Zoom', 'In', {'Speed': '1'})			

## Status Available (Ethernet)

For all commands, call Update to receive the latest status. ConnectionStatus does not support the Update function and is triggered by the device providing a successful response to other Update function calls.

Format with Qualifier:

```
InterfaceName.Update(Command, {'Qualifier Key': 'Qualifier Value'})
Value = InterfaceName.ReadStatus(Command, {'Qualifier Key': 'Qualifier Value'})
InterfaceName.SubscribeStatus(Command, {'Qualifier Key': 'Qualifier Value'},
```

FeedbackHandler)

FeedbackHandler will be called only when the specified qualifier gets a new status.

Format without Qualifier:

```
InterfaceName.Update(Command)
Value = InterfaceName.ReadStatus(Command)
InterfaceName.SubscribeStatus(Command, None, FeedbackHandler)
FeedbackHandler will be called when any qualifier gets a new status.
```

Command	Value	Value
AutoFocus	'On'	'Off'
# AutoFocus example InterfaceName.Update('AutoFocus') Value = InterfaceName.ReadStatus('AutoFocus') InterfaceName.SubscribeStatus('AutoFocus', None, FeedbackHandler)		
Command	Value	Value
AutoIris	'On'	'Off'
# AutoIris example InterfaceName.Update('AutoIris') Value = InterfaceName.ReadStatus('AutoIris') InterfaceName.SubscribeStatus('AutoIris', None, FeedbackHandler)		
Command	Value	Value
ConnectionStatus	'Connected'	'Disconnected'
# ConnectionStatus example Value = InterfaceName.ReadStatus('ConnectionStatus') InterfaceName.SubscribeStatus('ConnectionStatus', None, FeedbackHandler)		
Command	Value	
Iris	0 to 13 in steps of 1	
# Iris example InterfaceName.Update('Iris') Value = InterfaceName.ReadStatus('Iris') InterfaceName.SubscribeStatus('Iris', None, FeedbackHandler)		
Command	Value	Value
Power	'On'	'Off'
# Power example InterfaceName.Update('Power') Value = InterfaceName.ReadStatus('Power') InterfaceName.SubscribeStatus('Power', None, FeedbackHandler)		

## Cable and Adapter Requirements

Captive Screw to Male RJ45 connector.

## Notes for the Device

Device Baud Rate can be controlled by DIP Switches depending on the models. DIP switches can be located on the back of the camera or in the web interface on the System Page (DIP Switches tab).

## Serial communication

**Port Type:** RS-232

**Baud Rate:** 9600


**Data Bits:** 8

**Parity:** None


**Stop Bits:** One

**Flow Control:** None

## Pin Assignments Diagram



Signal	Main Cable	Pin	Signal
RxD	←	8	TxD
TxD	→	7	RxD
GND	→	6	GND



RJ-45 Camera

---

---

## Network communication

When configuring the Ethernet module, be sure device settings match those of the Global Scriptor ethernet interface.

**Port Type:** Ethernet (TCP)

**Default Port:** 23

**Logon Credentials Supported:** Yes

**Default Username:** admin

**Default Password:** password

**Multi-Connection:** Undetermined

**Capabilities:**

**Port Changeability:** Yes

---

---

## Ethernet Module Configuration Description

Please refer to user manual for settings and changes to the network communication.

## Notes for the Device

The Vaddio RoboSHOT camera system contains the physical camera and a 'OneLink' receiver. Both units receive unique IP addresses. When trying to control the camera via Ethernet, use the **IP address of the camera**, rather than the receiver.

**Appendix A. Set Commands(Serial)**

<b>Auto Focus Off</b>	\x81\x01\x048\x03\xff
<b>Auto Focus On</b>	\x81\x01\x048\x02\xff
<b>Backlight Off</b>	\x81\x01\x043\x03\xff
<b>Backlight On</b>	\x81\x01\x043\x02\xff
<b>Focus Far Speed 0</b>	\x81\x01\x04\x08 \xff
<b>Focus Far Speed 7</b>	\x81\x01\x04\x08' \xff
<b>Focus Near Speed 0</b>	\x81\x01\x04\x080\xff
<b>Focus Near Speed 7</b>	\x81\x01\x04\x087\xff
<b>Focus Stop Speed 0</b>	\x81\x01\x04\x08\x00\xff
<b>Focus Stop Speed 7</b>	\x81\x01\x04\x08\x00\xff
<b>Freeze Off</b>	\x81\x01\x04b\x03\xff
<b>Freeze On</b>	\x81\x01\x04b\x02\xff
<b>Iris Down</b>	\x81\x01\x04\x0B\x03\xff
<b>Iris Reset</b>	\x81\x01\x04\x0B\x00\xff
<b>Iris Up</b>	\x81\x01\x04\x0B\x02\xff
<b>Mute Off</b>	\x81\x01\x04u\x03\xff
<b>Mute On</b>	\x81\x01\x04u\x02\xff
<b>Pan Tilt Zoom Down Pan Speed 1 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x01\x00\x03\x02\x03\xff
<b>Pan Tilt Zoom Down Pan Speed 1 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x01\x07\x03\x02\x03\xff
<b>Pan Tilt Zoom Down Pan Speed 1 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x14\x00\x03\x02\x03\xff
<b>Pan Tilt Zoom Down Pan Speed 1 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x14\x07\x03\x02\x03\xff
<b>Pan Tilt Zoom Down Pan Speed 24 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x01\x00\x03\x02\x03\xff
<b>Pan Tilt Zoom Down Pan Speed 24 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x01\x07\x03\x02\x03\xff
<b>Pan Tilt Zoom Down Pan Speed 24 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x14\x00\x03\x02\x03\xff
<b>Pan Tilt Zoom Down Pan Speed 24 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x14\x07\x03\x02\x03\xff
<b>Pan Tilt Zoom In Pan Speed 1 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x01\x00\x03\x03\x01\xff
<b>Pan Tilt Zoom In Pan Speed 1 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x01\x07\x03\x03\x01\xff
<b>Pan Tilt Zoom In Pan Speed 1 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x14\x00\x03\x03\x01\xff
<b>Pan Tilt Zoom In Pan Speed 1 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x14\x07\x03\x03\x01\xff
<b>Pan Tilt Zoom In Pan Speed 24 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x01\x00\x03\x03\x01\xff
<b>Pan Tilt Zoom In Pan Speed 24 Tilt Speed 1 Zoom</b>	\x81\x01\x06\x0A\x18\x01\x07\x03\x03\x01\xff

<b>Speed 7</b>	
<b>Pan Tilt Zoom In Pan Speed 24 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x14\x00\x03\x03\x01\xFF
<b>Pan Tilt Zoom In Pan Speed 24 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x14\x07\x03\x03\x01\xFF
<b>Pan Tilt Zoom Left Pan Speed 1 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x01\x00\x01\x03\x03\xFF
<b>Pan Tilt Zoom Left Pan Speed 1 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x01\x07\x01\x03\x03\xFF
<b>Pan Tilt Zoom Left Pan Speed 1 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x14\x00\x01\x03\x03\xFF
<b>Pan Tilt Zoom Left Pan Speed 1 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x14\x07\x01\x03\x03\xFF
<b>Pan Tilt Zoom Left Pan Speed 24 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x01\x00\x01\x03\x03\xFF
<b>Pan Tilt Zoom Left Pan Speed 24 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x01\x07\x01\x03\x03\xFF
<b>Pan Tilt Zoom Left Pan Speed 24 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x14\x00\x01\x03\x03\xFF
<b>Pan Tilt Zoom Left Pan Speed 24 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x14\x07\x01\x03\x03\xFF
<b>Pan Tilt Zoom Out Pan Speed 1 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x01\x00\x03\x03\x02\xFF
<b>Pan Tilt Zoom Out Pan Speed 1 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x01\x07\x03\x03\x02\xFF
<b>Pan Tilt Zoom Out Pan Speed 1 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x14\x00\x03\x03\x02\xFF
<b>Pan Tilt Zoom Out Pan Speed 1 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x14\x07\x03\x03\x02\xFF
<b>Pan Tilt Zoom Out Pan Speed 24 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x01\x00\x03\x03\x02\xFF
<b>Pan Tilt Zoom Out Pan Speed 24 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x01\x07\x03\x03\x02\xFF
<b>Pan Tilt Zoom Out Pan Speed 24 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x14\x00\x03\x03\x02\xFF
<b>Pan Tilt Zoom Out Pan Speed 24 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x14\x07\x03\x03\x02\xFF
<b>Pan Tilt Zoom Right Pan Speed 1 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x01\x00\x02\x03\x03\xFF
<b>Pan Tilt Zoom Right Pan Speed 1 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x01\x07\x02\x03\x03\xFF
<b>Pan Tilt Zoom Right Pan Speed 1 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x14\x00\x02\x03\x03\xFF
<b>Pan Tilt Zoom Right Pan Speed 1 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x14\x07\x02\x03\x03\xFF
<b>Pan Tilt Zoom Right Pan Speed 24 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x01\x00\x02\x03\x03\xFF

<b>Pan Tilt Zoom Right Pan Speed 24 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x01\x07\x02\x03\x03\xFF
<b>Pan Tilt Zoom Right Pan Speed 24 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x14\x00\x02\x03\x03\xFF
<b>Pan Tilt Zoom Right Pan Speed 24 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x14\x07\x02\x03\x03\xFF
<b>Pan Tilt Zoom Stop Pan Speed 1 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x01\x00\x03\x03\x03\xFF
<b>Pan Tilt Zoom Stop Pan Speed 1 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x01\x07\x03\x03\x03\xFF
<b>Pan Tilt Zoom Stop Pan Speed 1 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x14\x00\x03\x03\x03\xFF
<b>Pan Tilt Zoom Stop Pan Speed 1 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x14\x07\x03\x03\x03\xFF
<b>Pan Tilt Zoom Stop Pan Speed 24 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x01\x00\x03\x03\x03\xFF
<b>Pan Tilt Zoom Stop Pan Speed 24 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x01\x07\x03\x03\x03\xFF
<b>Pan Tilt Zoom Stop Pan Speed 24 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x14\x00\x03\x03\x03\xFF
<b>Pan Tilt Zoom Stop Pan Speed 24 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x14\x07\x03\x03\x03\xFF
<b>Pan Tilt Zoom Up Pan Speed 1 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x01\x00\x03\x01\x03\xFF
<b>Pan Tilt Zoom Up Pan Speed 1 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x01\x07\x03\x01\x03\xFF
<b>Pan Tilt Zoom Up Pan Speed 1 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x01\x14\x00\x03\x01\x03\xFF
<b>Pan Tilt Zoom Up Pan Speed 1 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x01\x14\x07\x03\x01\x03\xFF
<b>Pan Tilt Zoom Up Pan Speed 24 Tilt Speed 1 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x01\x00\x03\x01\x03\xFF
<b>Pan Tilt Zoom Up Pan Speed 24 Tilt Speed 1 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x01\x07\x03\x01\x03\xFF
<b>Pan Tilt Zoom Up Pan Speed 24 Tilt Speed 20 Zoom Speed 0</b>	\x81\x01\x06\x0A\x18\x14\x00\x03\x01\x03\xFF
<b>Pan Tilt Zoom Up Pan Speed 24 Tilt Speed 20 Zoom Speed 7</b>	\x81\x01\x06\x0A\x18\x14\x07\x03\x01\x03\xFF
<b>Power Off</b>	\x81\x01\x04\x00\x03\xFF
<b>Power On</b>	\x81\x01\x04\x00\x02\xFF
<b>Preset Recall 1</b>	\x81\x01\x04?\x02\x00\xFF
<b>Preset Recall 16</b>	\x81\x01\x04?\x02\x0F\xFF
<b>Preset Save 1</b>	\x81\x01\x04?\x01\x00\xFF
<b>Preset Save 16</b>	\x81\x01\x04?\x01\x0F\xFF
<b>Recall Tri-Sync 0</b>	\x81\x01\x04?\x12\x00\xFF
<b>Recall Tri-Sync 15</b>	\x81\x01\x04?\x12\x0F\xFF

**Global Scriptor Module  
Communication Sheet**

Revision: 12/1/2022

---

<b>Set Tri-Sync 0 Speed 1</b>	\x81\x01\x04?1\x00\x00\x01\xff
<b>Set Tri-Sync 0 Speed 26</b>	\x81\x01\x04?1\x00\x01\x0A\xff
<b>Set Tri-Sync 15 Speed 1</b>	\x81\x01\x04?1\x0F\x00\x01\xff
<b>Set Tri-Sync 15 Speed 26</b>	\x81\x01\x04?1\x0F\x01\x0A\xff
<b>White Balance ATW</b>	\x81\x01\x045\x04\xff
<b>White Balance Auto</b>	\x81\x01\x045\x00\xff
<b>White Balance Indoor</b>	\x81\x01\x045\x01\xff
<b>White Balance Manual</b>	\x81\x01\x045\x05\xff
<b>White Balance One Push Trigger</b>	\x81\x01\x04\x10\x05\xff
<b>White Balance One Push White Balance</b>	\x81\x01\x045\x03\xff
<b>White Balance Outdoor</b>	\x81\x01\x045\x02\xff
<b>White Balance Outdoor Auto</b>	\x81\x01\x045\x06\xff
<b>White Balance Sodium Lamp</b>	\x81\x01\x045\x08\xff
<b>White Balance Sodium Lamp Auto</b>	\x81\x01\x045\x07\xff
<b>White Balance Sodium Lamp Outdoor Auto</b>	\x81\x01\x045\x09\xff

---

## Appendix B. Update Commands(Serial)

<b>Auto Focus</b>	\x81\x09\x048\xff
<b>Backlight</b>	\x81\x09\x043\xff
<b>Freeze</b>	\x81\x09\x04b\xff
<b>Mute</b>	\x81\x09\x04u\xff
<b>Power</b>	\x81\x09\x04\x00\xff
<b>White Balance</b>	\x81\x09\x045\xff

**Appendix C. Set Commands(Ethernet)**

<b>Auto Focus Off</b>	camera focus mode manual\x0D\x0A
<b>Auto Focus On</b>	camera focus mode auto\x0D\x0A
<b>Auto Iris Off</b>	camera ccu set auto_iris off\x0D\x0A
<b>Auto Iris On</b>	camera ccu set auto_iris on\x0D\x0A
<b>Focus Far Speed 0</b>	camera focus far 1\x0D\x0A
<b>Focus Far Speed 7</b>	camera focus far 8\x0D\x0A
<b>Focus Near Speed 0</b>	camera focus near 1\x0D\x0A
<b>Focus Near Speed 7</b>	camera focus near 8\x0D\x0A
<b>Focus Stop Speed 0</b>	camera focus stop\x0D\x0A
<b>Focus Stop Speed 7</b>	camera focus stop\x0D\x0A
<b>Iris 0</b>	camera ccu set iris 0\x0D\x0A
<b>Iris 13</b>	camera ccu set iris 13\x0D\x0A
<b>Iris Down</b>	camera ccu set iris Down\x0D\x0A
<b>Iris Reset</b>	camera ccu set iris Reset\x0D\x0A
<b>Iris Up</b>	camera ccu set iris Up\x0D\x0A
<b>Pan Left Speed 1</b>	camera pan left 1\x0D\x0A
<b>Pan Left Speed 24</b>	camera pan left 24\x0D\x0A
<b>Pan Left Speed Default</b>	camera pan left\x0D\x0A
<b>Pan Right Speed 1</b>	camera pan right 1\x0D\x0A
<b>Pan Right Speed 24</b>	camera pan right 24\x0D\x0A
<b>Pan Right Speed Default</b>	camera pan right\x0D\x0A
<b>Pan Stop Speed 1</b>	camera pan stop\x0D\x0A
<b>Pan Stop Speed 24</b>	camera pan stop\x0D\x0A
<b>Pan Stop Speed Default</b>	camera pan stop\x0D\x0A
<b>Power Off</b>	camera standby on\x0D\x0A
<b>Power On</b>	camera standby off\x0D\x0A
<b>Preset Recall 1</b>	camera preset recall 1\x0D\x0A
<b>Preset Recall 16</b>	camera preset recall 16\x0D\x0A
<b>Preset Save 1</b>	camera preset store 1\x0D\x0A
<b>Preset Save 16</b>	camera preset store 16\x0D\x0A
<b>Tilt Down Speed 1</b>	camera tilt down 1\x0D\x0A
<b>Tilt Down Speed 20</b>	camera tilt down 20\x0D\x0A
<b>Tilt Down Speed Default</b>	camera tilt down\x0D\x0A
<b>Tilt Stop Speed 1</b>	camera tilt stop\x0D\x0A
<b>Tilt Stop Speed 20</b>	camera tilt stop\x0D\x0A
<b>Tilt Stop Speed Default</b>	camera tilt stop\x0D\x0A
<b>Tilt Up Speed 1</b>	camera tilt up 1\x0D\x0A
<b>Tilt Up Speed 20</b>	camera tilt up 20\x0D\x0A
<b>Tilt Up Speed Default</b>	camera tilt up\x0D\x0A
<b>Zoom In Speed 1</b>	camera zoom in 1\x0D\x0A
<b>Zoom In Speed 7</b>	camera zoom in 7\x0D\x0A
<b>Zoom In Speed Default</b>	camera zoom in\x0D\x0A

## Global Scriptor Module Communication Sheet

---

<b>Zoom Out Speed 1</b>	camera zoom out 1\x0D\x0A
<b>Zoom Out Speed 7</b>	camera zoom out 7\x0D\x0A
<b>Zoom Out Speed Default</b>	camera zoom out\x0D\x0A
<b>Zoom Stop Speed 1</b>	camera zoom stop\x0D\x0A
<b>Zoom Stop Speed 7</b>	camera zoom stop\x0D\x0A
<b>Zoom Stop Speed Default</b>	camera zoom stop\x0D\x0A

---

## Appendix D. Update Commands(Ethernet)

<b>Auto Focus</b>	camera focus mode get\x0D\x0A
<b>Auto Iris</b>	camera ccu get auto_iris\x0D\x0A
<b>Iris</b>	camera ccu get iris\x0D\x0A
<b>Power</b>	camera standby get\x0D\x0A